

CPU Pinning

How to do CPU pinning (work in progress)

Create a file under `/etc/pve/qemu-server/$vmid.cpuset` for the VM which you want to set the CPU pinning for.

Examples:

```
0-1
```

```
0-1, 6-7
```

Depending on your [CPU topology](#) assign the proper cores to your VM. You can find the topology out by running `lscpu -e`

Next create a file called `taskset-hook.sh` and save it under `/var/lib/vz/snippets/`, create the snippets folder if it's not there already and make the script executable.

Content:

```
#!/bin/bash

vmid="$1"
phase="$2"

if [[ "$phase" == "post-start" ]]; then
    main_pid="$(< /run/qemu-server/$vmid.pid)"

    #cpuset="0-11"
    cpuset="$(< /etc/pve/qemu-server/$vmid.cpuset)"

    taskset --cpu-list --all-tasks --pid "$cpuset" "$main_pid"
fi
```

```
mkdir /var/lib/vz/snippets
cp taskset-hook.sh /var/lib/vz/snippets
chmod +x /var/lib/vz/snippets/taskset-hook.sh
```

Finally set the script to the VM:

```
qm set VMID --hookscript local:snippets/taskset-hook.sh
```

If for some reason the script is not working for you or you just want it to be removed, simply open `/etc/pve/qemu-server/VMID.conf` and remove the script.

Sources:

- <https://forum.proxmox.com/threads/cpu-pinning.67805/post-304715>
- https://wiki.archlinux.org/index.php/PCI_passthrough_via_OVMF#Performance_tuning

Revision #8

Created 30 April 2022 04:44:50 by Tozo

Updated 15 May 2022 03:24:27 by Tozo